

# Quantum Dissipative Systems and Feedback Control Design by Interconnection

Matthew R. James, John Gough

## Abstract

The purpose of this paper is to extend J.C. Willems' theory of dissipative systems to the quantum domain. This general theory, which combines perspectives from the quantum physics and control engineering communities, provides useful methods for analysis and design of dissipative quantum systems. We describe the interaction of the plant and a class of exosystems in general quantum feedback network terms. Our results include an infinitesimal characterization of the dissipation property, which generalizes the well-known Positive Real and Bounded Real Lemmas, and is used to study some properties of quantum dissipative systems. We also show how to formulate control design problems using quantum network models, which implements Willems' "control by interconnection" for open quantum systems. This control design formulation includes, for example, standard problems of stabilization, regulation, and robust control.

**Keywords:** Quantum feedback control, dissipation, damping, quantum feedback networks, control by interconnection, regulation, stabilization, robustness.

## I. INTRODUCTION

In 1972 J.C. Willems [34] developed a general theory of dissipative systems for the purpose of stability analysis of open systems, that is, systems that may be subject to external influences, [36]. This theory generalizes Lyapunov methods that apply to closed systems, as well as important results in control theory including the positive and bounded real lemmas. The theory is widely used in control system analysis and design. In particular, methods for stability analysis, e.g. [21], [14], [15], control design by energy shaping, interconnection, robust control system design; e.g. [26], [32], [35], [36], [28], [37] have been developed. While Willems' theory applies to quite general nonlinear systems, it has its origins in classical physical systems and is based on describing energy storage and flows. As a simple example, consider the passive series RLC circuit of Figure 1. Energy  $V = \frac{L}{2}\dot{q}^2 + \frac{1}{2C}q^2$  is stored in the inductor and the capacitor (here,  $L$  is the impedance,  $C$  is the capacitance,  $q$  is capacitor charge, and  $i$  is the current). The external voltage  $v$  is related to the internal voltages by  $v = v_L + v_R + v_C$ , with  $v_L = L\ddot{q}$ ,  $v_R = R\dot{q}$  and  $v_C = \frac{1}{C}q$ , and this determines the dynamical equation  $\frac{di}{dt} = \frac{1}{L}(v - Ri - \frac{1}{C}q)$ . The rate of change of stored energy is given by

$$\dot{V} = -Ri^2 + vi. \quad (1)$$

M.R. James is with the Department of Engineering, Australian National University, Canberra, ACT 0200, Australia. Matthew.James@anu.edu.au. Research supported by the Australian Research Council.

J. Gough is with the Institute for Mathematical and Physical Sciences, University of Wales, Aberystwyth, Ceredigion, SY23 3BZ, Wales. jug@aber.ac.uk

The first term on the RHS is the energy dissipated by the resistor, and the second term is the power applied to the circuit by an external source. This expression describes the balance of energy flows, and implies the inequality

$$\dot{V} \leq vi, \quad (2)$$

which is an example (in differential form) of the *dissipation inequalities* considered by Willems. It says simply that the rate at which energy is stored must be less than the rate at which energy is supplied; the remainder being dissipated. Inequalities of this type are of fundamental importance to stability analysis of open systems. Furthermore, such inequalities can be exploited to facilitate control system design. Because of the emerging need for analysis and design methods for quantum technologies, the purpose of this paper is to develop an analogous framework for open quantum systems.




Fig. 1. Series RLC circuit.

The types of open quantum systems we consider include the optical cavity shown in Figure 2, which consists of a pair of mirrors (one of which is partially transmitting) supporting a trapped mode of light. This cavity mode may interact with a free external optical field through the partially transmitting mirror. The external field consists of two components: the input field, which is the field before it has interacted with the cavity mode, and the output field, being the field after interaction. The output field may carry away energy, and in this way the cavity system dissipates energy. This quantum system is in some ways analogous to the RLC circuit discussed above, which stores electromagnetic energy in the inductor and capacitor, but loses energy as heat through the resistor. The cavity also stores electromagnetic energy, quantized as photons, and these may be lost to the external field. If  $V$  denotes the physical observable for the energy of the cavity mode, and if a laser beam is applied as an input  $w$ , then the energy dissipation relation for the cavity is of the form

$$\mathcal{G}(V) \leq z^*w + w^*z, \quad (3)$$

where  $z$  is a physical quantity of the cavity (notation is explained at the end of this section). The term  $\mathcal{G}(V)$  plays the role of  $\dot{V}$ , and is discussed further in sections II-A and II-D. This inequality relates the rate at which energy is stored in the cavity to the rate at which energy is supplied, with the remainder being lost to the external field (which serves as a heat bath).

Our principal goal in this paper is to formalize a notion of dissipation for open quantum systems in a way that is helpful for quantum control analysis and design by combining perspectives from control engineering with




Fig. 2. A cavity consists of a pair of mirrors, one of which is perfectly reflecting (shown solid) while the other is partially transmitting (shown unfilled). The partially transmitting mirror enables the light mode inside the cavity to interact with an external light field, such as a laser beam. The external field is separated into input and output components by a Faraday isolator.

perspectives from quantum physics. Indeed, phenomena of *dissipation* or *damping* are fundamental in both physics and engineering, and have been the subject of extensive investigations. In physics, methods have been developed to model energy loss and decoherence (loss of quantum coherence) arising from the interaction of a system with an environment, or heat bath, [25], [42], [16], [9], [2], [10]. Open quantum models are unitary models that provide a description of the system of interest, or *plant* (e.g. optical cavity, atom, etc) as well as the environment (e.g. optical field), where the influence of the environment on the system may be described with the aid of *quantum noise*. These models preserve the essential nature of quantum mechanics, a feature of basic importance.

Our modeling of dissipative quantum systems has its origins in the papers [7], [6], [4], [17], and represents inputs as the sum of a quantum noise term, used in physics to describe damping as mentioned above, and a signal term of the type used by Willems to provide a means for the external world to influence the system. This signal plus noise representation arises in a natural way in the unitary models we use. The signal component of the input comes from the output of another system, which we call an *exosystem*. We develop our framework for quantum dissipative systems by using open quantum model descriptions of *quantum networks*, [12], [11], [8], [3], [40], [41]. We therefore employ a network description of a plant interacting with an exosystem. We allow the exosystem to vary in a class of such exosystems, and the dissipation inequality we define is expressed in these terms. This network description turns out to be very appropriate and efficient, and was inspired by the behavioral “control as interconnection” perspective in Willems’ more recent work, [35], [36] (also [31], [30], [38]). We provide an infinitesimal characterization of the dissipation property, and this important tool is used indispensably in this paper. This characterization includes generalizations of the well-known Positive Real and Bounded Real Lemmas, and is used to study some properties of quantum dissipative systems. We show that essentially all open quantum systems are dissipative for a suitable choice of supply rate. This “natural” supply rate includes terms corresponding to the classical notion of *passivity*, a dissipation or damping term due to the quantum noise, and a dissipative term which is present in general when the exosystem does not commute with the plant.

The framework we develop can also be used to describe how systems are influenced by controllers, and hence is useful for control design by interconnection, [35], [36], and various passivity-based methods [26], [32], [27], [28].

We give a general description of how to formulate control design problems in these terms. This description includes, for example, standard problems of stabilization, regulation, and robust control. It is important to appreciate that because we express control design problems in terms of unitary models, the controllers obtained can (in principle) be physically realized—this is vital when we wish, for instance, the controller to be itself a quantum system, as in *coherent control*, [18], [39], [17], [24], [23], [19].

Note that issues of stability are important in the analysis and design of quantum networks. This is because quantum networks may contain active elements that introduce energy, and whenever this happens, stability of feedback loops in the network is a basic consideration (small gain theorem, [43], [44], [4]). Energy may be introduced by design, such as via an amplifier, or by accident due to undesirable environmental influences. It also plays a role in regulation of a system to a desired equilibrium mode of operation.

We begin in section II by describing the mathematical models for quantum feedback networks we use, which are expressed in terms of the quantum stochastic calculus, [16], [9]. This section includes some material aimed at helping orient the reader to the ideas, models and notation used in the remainder of this paper. Our main definitions and results for quantum dissipative systems are given in section III, which includes some examples for illustration. Section IV contains a formulation of control by interconnection methodology for quantum dissipative systems, which we illustrate using simple examples. The appendix contains some definitions and results needed in the paper.

*Background references.* A number of articles and books are available to help readers with the background material on which the present paper is based. The papers [40] and [33] provide excellent introductions to aspects of the quantum models we use. The paper [1] is a tutorial article written to assist control theorists and engineers by providing introductory discussions of quantum mechanics, open quantum stochastic models, and quantum filtering. The book [10] is an invaluable resource for quantum noise models and quantum optics, while the book [29] provides a detailed mathematical treatment of the Hudson-Parthasarathy theory of the quantum stochastic calculus. The book [20] is a standard textbook on quantum mechanics. The papers [12] and [11] contain the basic results concerning quantum feedback networks used in this paper.

*Notation.* In this paper we use matrices  $M = \{m_{ij}\}$  with entries  $m_{ij}$  that are operators on an underlying Hilbert space. The asterisk  $*$  is used to indicate the Hilbert space adjoint  $A^*$  of an operator  $A$ , as well as the complex conjugate  $z^* = x - iy$  of a complex number  $z = x + iy$  (here,  $i = \sqrt{-1}$  and  $x, y$  are real). Real and imaginary parts are denoted  $\text{Re}(z) = (z + z^*)/2$  and  $\text{Im}(z) = -i(z - z^*)/2$  respectively. The conjugate transpose  $M^\dagger$  of a matrix  $M$  is defined by  $M^\dagger = \{m_{ji}^*\}$ . Also defined are the conjugate  $M^* = \{m_{ij}^*\}$  and transpose  $M^T = \{m_{ji}\}$  matrices, so that  $M^\dagger = (M^T)^* = (M^*)^T$ . In the physics literature, it is common to use the dagger  $\dagger$  to indicate the Hilbert space adjoint. The commutator of two operators  $A, B$  is defined by  $[A, B] = AB - BA$ .  $\delta(\cdot)$  is the Dirac delta function, and  $\delta_{jk}$  is the Kronecker delta. The tensor product of operators  $A, B$  defined on Hilbert spaces  $H, G$  is an operator  $A \otimes B$  defined on the Hilbert space  $H \otimes G$  (tensor product of Hilbert spaces) defined by  $(A \otimes B)(\psi \otimes \phi) = (A\psi) \otimes (B\phi)$  for  $\psi \in H, \phi \in G$ ; we usually follow the standard shorthand and write simply  $AB = A \otimes B$  for the tensor product, and also  $A = A \otimes I$  and  $B = I \otimes B$ .

## II. PRELIMINARIES

### A. The Classical RLC Circuit Revisited

Before embarking on a description of the class of open quantum systems considered in this paper, we revisit the simple classical RLC circuit of Figure 1 in order to provide some conceptual and notational connections with the quantum theory. We may choose the charge and current as the “state variables” for the circuit. That is  $x = (q, i)^T$  give global coordinates for the state space manifold which is here a phase-plane, and the trajectories are then the solutions to the system of equations  $\frac{dq}{dt} = w_v^q(q, i)$ ,  $\frac{di}{dt} = w_v^i(q, i)$ , where  $w_v^q(q, i) = i$  and  $w_v^i(q, i) = \frac{1}{L}(v - Ri - \frac{1}{C}q)$ . Alternatively, the trajectories  $x(t) = (q(t), i(t))^T$  can be thought of as the integral curves to the tangent vector field

$$w_v(q, i) = w_v^q(q, i) \frac{\partial}{\partial q} + w_v^i(q, i) \frac{\partial}{\partial i}; \quad (4)$$

i.e. solutions to the differential equation

$$\dot{x} = w_v(x). \quad (5)$$

Note that we need to prescribe the value of the external voltage  $v$ , possibly as a function of time, and that  $w_v$  actually corresponds to a family of tangent vector fields generating a controlled flow.

For an arbitrary smooth function  $f(x) = f(q, i)$  of the state, we have by the chain rule

$$\frac{d}{dt}f(x(t)) = w_v^q(x(t)) \frac{\partial f}{\partial q}(x(t)) + w_v^i(x(t)) \frac{\partial f}{\partial i}(x(t)), \quad (6)$$

or in compact form

$$\dot{f} = \mathcal{G}_v(f) \quad (7)$$

where  $\mathcal{G}_v(f)$  is the directional derivative operator

$$\mathcal{G}_v(f) = \nabla f \cdot w_v. \quad (8)$$

In particular, the stored energy  $V = \frac{L}{2}i^2 + \frac{1}{2C}q^2$  is a quadratic function of the state variables, and the energy balance equation (1) is obtained from setting  $f = V$ :

$$\dot{V} = \mathcal{G}_v(V) \equiv r^0(v), \quad (9)$$

where  $r^0(v)$  is the function  $-Ri^2 + iv$  on the phase plane, also dependent on the input voltage  $v$ .

The energy balance relation (1) and dissipation inequality (2) become

$$\mathcal{G}_v(V) - r^0(v) = 0, \quad (10)$$

and

$$\mathcal{G}_v(V) - r(v) \leq 0, \quad (11)$$

where the respective supply rates are  $r^0(v) = -Ri^2 + iv$  and  $r(v) = iv$ . If we regard the voltage  $v$  as an input and the current  $i$  as an output function of the phase space variables, then it can be seen that the supply rates are functions of the phase space variables and the input.

Functions  $f = f(q, i)$  of the phase space variables correspond to the physical variables of interest, and are basic to any description of classical mechanics. When considering open physical systems, such as the RLC circuit, or the open quantum systems discussed in this paper, it is helpful to have a notation for indicating to which physical system a physical variable belongs. If we write  $\mathcal{A}_{RLC}$  for RLC circuit physical variables (the set of smooth functions on the phase space manifold) then this is in fact a commutative algebra which may be extended to a  $*$ -algebra by taking complex-valued functions with the choice of complex conjugation as the  $*$ -operation. Likewise we could write  $\mathcal{A}_{ex}$  for functions of the external variables  $v$ . We then see that the energy function  $V$  belongs to  $\mathcal{A}_{RLC}$ . The supply rates however belong to the algebra of functions over both state variables and external variables, the tensor product  $\mathcal{A}_{RLC} \otimes \mathcal{A}_{ex}$ , so that  $r^0, r \in \mathcal{A}_{RLC} \otimes \mathcal{A}_{ex}$ . In the quantum setting, these algebras will be non-commutative (in fact algebras of operators over Hilbert spaces).

The crucial observation is that the energy balance relation (1) and the dissipation inequality (2) are to hold for all input signals  $v$ . This can be re-expressed as saying that (1) and (2) hold for all external signal generators  $v$ , as shown in Figure 3. This leads to an interpretation of energy balance and dissipation inequalities in terms of an interconnected system consisting of the principal system of interest (the RLC circuit) and an exosystem (the signal generator). This interpretation will be used in the quantum context in section III below.




Fig. 3. Series RLC circuit connected to an external signal generator.

### B. Quantum Mechanics

In quantum mechanics [20] physical quantities like energy, spin, position, etc., are expressed as *observables*; these are represented as self-adjoint operators acting on a Hilbert space  $\mathcal{H}$ . Other physical variables, like annihilation operators (see Appendix B)—which are not self-adjoint—are also of importance. We will use the notation  $\mathcal{A}$  to refer to the collection of physical variables for a system (in general  $\mathcal{A}$  is a non-commutative  $*$ -algebra). We refer to  $\mathcal{A}$  as the *physical variable space* for the system. Unit vectors  $\psi \in \mathcal{H}$  are called *state vectors*. When a quantum system is in a state defined by a state vector  $\psi \in \mathcal{H}$ , the expected value of an observable  $A \in \mathcal{A}$  is defined in terms of the Hilbert space inner product:  $\langle \psi, A\psi \rangle$ . In what follows we use the shorthand notation  $\langle A \rangle$  to denote expectation when the underlying state is understood.

The postulates of quantum mechanics state that for a closed system the evolution of states and observables are

given in terms of a unitary operator  $U(t)$  satisfying the Schrödinger equation

$$\dot{U} = -iHU, \quad (12)$$

with initial condition  $U(0) = I$  (the identity). Here,  $H$  is an observable called the *Hamiltonian*, and represents the energy of the system. State vectors evolve according to  $\psi_t = U(t)\psi$ . Alternatively, we may view state vectors as fixed in time, while observables are taken to evolve according to  $A(t) = U^*(t)AU(t)$ : this is the Heisenberg picture. Both pictures are equivalent and the average of an observable  $A$  in state  $\psi$  at time  $t$  is given equally by  $\langle \psi, A\psi \rangle_t = \langle \psi_t, A\psi_t \rangle = \langle \psi, A(t)\psi \rangle$ .

In this paper we are interested in open quantum systems - systems that interact with other systems or an environment. These systems will be defined in section II-D in terms of a stochastic generalization of the Schrodinger equation (12) involving quantum noise. Before considering these open system models, we look at a simple situation of two interacting systems in the next section.

### C. A Pair of Interacting Systems

Consider a pair of independent systems  $P$  (the plant) and  $W$  (the exosystem, or signal generator). The physical variable spaces for these systems are denoted  $\mathcal{A}_P$  and  $\mathcal{A}_W$  respectively, and consist of operators defined on underlying Hilbert spaces  $H_P$  and  $H_W$  respectively. The physical variable space for the combined system is the tensor product  $\mathcal{A}_P \otimes \mathcal{A}_W$ , consisting of operators on the Hilbert space  $H_P \otimes H_W$ . All operators in  $\mathcal{A}_P$  may be regarded as operators in  $\mathcal{A}_P \otimes \mathcal{A}_W$  by identifying  $A_P$  with  $A_P \otimes I_W$ , and similarly for  $\mathcal{A}_W$ . As a consequence, all variables in  $\mathcal{A}_P$  commute with all variables in  $\mathcal{A}_W$ .

Let  $H_P \in \mathcal{A}_P$  and  $H_W \in \mathcal{A}_W$  be the Hamiltonians for each of the systems, respectively; this would be enough to specify their dynamics as isolated, closed, systems. However, we allow them to interact by exchanging energy as specified by the *interaction Hamiltonian*

$$H_{PW} = -i(K^*v - v^*K), \quad (13)$$

where  $K \in \mathcal{A}_P$  and  $v \in \mathcal{A}_W$ . The total Hamiltonian for the combined system is  $H = H_P + H_W + H_{PW}$ , and the dynamics are given by the Schrödinger equation (12) using this total Hamiltonian.

Now let's consider the effect of the exosystem  $W$  on the plant  $P$ . Let  $V \in \mathcal{A}_P$  be a non-negative observable that commutes with  $H_P$ . Then from (12) we see that  $V$  evolves according to

$$\begin{aligned} \dot{V} &= -i[V, H] \\ &= v^*[V, K] - [V, K^*]v \\ &= Z^*v + v^*Z, \end{aligned} \quad (14)$$

where  $Z = [V, K] \in \mathcal{A}_P$ . From this we see that  $P$  is lossless, with the RHS of (14) giving the net rate at which energy is delivered to  $P$  from  $W$  (cf. [32, eq. (2.39) and Chapter 4], and section III-A below).

In the general framework we present in this paper (section III),  $P$  is an open system, and  $W$  may be connected to  $P$  via field connections in addition to direct couplings of the form (13). Open quantum systems are summarized in section II-D, and mechanisms for interconnecting them are reviewed in section II-E.

#### D. Definitions

We consider an open quantum system  $G$  with physical variable space  $\mathcal{A}_G$  consisting of operators  $X$  defined on an underlying Hilbert space  $\mathcal{H}_G$ . The self-energy of this system is described by a Hamiltonian  $H \in \mathcal{A}_G$ . This system is driven by a collection of  $n$  field channels given by the quantum stochastic processes

$$A = \begin{pmatrix} A_1 \\ \vdots \\ A_n \end{pmatrix}, \quad \Lambda = \begin{pmatrix} A_{11} & \dots & A_{1n} \\ \vdots & \ddots & \vdots \\ A_{n1} & \dots & A_{nn} \end{pmatrix}.$$

These respectively describe annihilation of photons in the field channels, and scattering between channels, and are operators on a Hilbert space  $\mathcal{F}$ , with associated variable space  $\mathcal{F}$ . Specifically,  $\mathcal{F}$  is the Hilbert space describing an indefinite number of quanta (called a Fock space [29]), and  $\mathcal{F}$  is the space of operators over this space. We assume that these processes are *canonical*, meaning that we have the following non-vanishing second order Ito products:  $dA_j(t) dA_k(t)^* = \delta_{jk} dt$ ,  $dA_{jk}(t) dA_l(t)^* = \delta_{kl} dA_j(t)^*$ ,  $dA_j(t) dA_{kl}(t) = \delta_{jk} dA_l(t)$  and  $dA_{jk}(t) dA_{lm}(t) = \delta_{kl} dA_{jm}(t)$ . The simplest situation corresponds to that of a vacuum state  $\phi \in \mathcal{F}$  for the field channels, in which case the input processes are purely quantum noise.

Coupling of the system to the field is defined using

$$S = \begin{pmatrix} S_{11} & \dots & S_{1n} \\ \vdots & \ddots & \vdots \\ S_{n1} & \dots & S_{nn} \end{pmatrix}, \quad L = \begin{pmatrix} L_1 \\ \vdots \\ L_n \end{pmatrix},$$

respectively a *scattering matrix* with operator entries  $S_{ij} \in \mathcal{A}_G$  satisfying  $S^\dagger S = S S^\dagger = I$ , and a vector of *coupling operators*  $L_j \in \mathcal{A}_G$ .

In terms of the parameters  $G = (S, L, H)$ , the Schrodinger equation

$$dU(t) = \left\{ \text{tr}[(S - I)d\Lambda] + dA^\dagger L - L^\dagger S dA - \frac{1}{2} L^\dagger L dt - iH dt \right\} U(t) \quad (15)$$

with initial condition  $U(0) = I$  determines the unitary motion of the system, in accordance with the fundamental postulate of quantum mechanics. Given a system operator  $X \in \mathcal{A}_G$ , its Heisenberg evolution is defined by  $X(t) = j_t(X) = U(t)^* X U(t)$  and satisfies

$$\begin{aligned} dX(t) &= (\mathcal{L}_{L(t)}(X(t)) - i[X(t), H(t)])dt \\ &+ dA^\dagger(t) S^\dagger(t) [X(t), L(t)] + [L^\dagger(t), X(t)] S(t) dA(t) \\ &+ \text{tr}[(S^\dagger(t) X(t) S(t) - X(t)) d\Lambda(t)]. \end{aligned} \quad (16)$$



In this expression, all operators evolve unitarily (e.g.  $L(t) = j_t(L)$ ) (commutators of vectors and matrices of operators are defined component-wise), and  $\text{tr}$  denotes the trace of a matrix. We also employ the notation

$$\mathcal{L}_L(X) = \frac{1}{2}L^\dagger[X, L] + \frac{1}{2}[L^\dagger, X]L. \quad (17)$$

In what follows we write

$$\mathcal{G}_G(X) = -i[X, H] + \mathcal{L}_L(X) \quad (18)$$

for the *generator* of the plant  $G$ . The components of the output fields are defined by  $\tilde{A}(t) = j_t(A(t)) \doteq U^*(t)A(t)U(t)$ ,  $\tilde{\Lambda}(t) = j_t(\Lambda(t)) \doteq U^*(t)\Lambda(t)U(t)$  and satisfy the quantum stochastic differential equations

$$d\tilde{A}(t) = S(t)dA(t) + L(t)dt \quad (19)$$

$$d\tilde{\Lambda}(t) = S^*(t)d\Lambda(t)S^T(t) + S^*(t)dA^*(t)L^T(t) \quad (20)$$

$$+L(t)dA(t)S^T(t) + L^*(t)L^T(t)dt, \quad (21)$$

where  $L(t) = j_t(L)$ , etc., as above. The output processes also have canonical quantum Ito products.

It can be seen that the parameters  $G = (S, L, H)$  provide a compact specification of the open system, assuming canonical field inputs, since they determine the behavior of the system, via the flow  $j_t(\cdot)$ , as determined by the Schrodinger equation (15). In the case of a purely static system, we sometimes use the shorthand  $S = (S, 0, 0)$ . Important special cases are  $I = (I, 0, 0)$ , the trivial (identity) system, and  $J = (J, 0, 0)$ , where

$$J = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}.$$

If  $\psi \in \mathcal{H}_G$  is an initial system state vector, then with vacuum fields the state vector of the complete system is  $\psi \otimes \phi$ . Then the quantum expectation  $\langle X(t) \rangle$  is defined to be  $\langle \psi \otimes \phi, X(t)\psi \otimes \phi \rangle$ . In order to describe how quantum noise beyond time  $t$  is averaged out, we introduce a collection  $\{\mathcal{F}_t\}$  of physical variable spaces such that  $\mathcal{F}_t \subset \mathcal{A}_G \otimes \mathcal{F}$  is generated by operators in  $\mathcal{A}_G$  and the quantum noises  $A_{ij}(s)$ ,  $s \leq t$ . Then  $X(t)$  is adapted, i.e.  $X(t) \in \mathcal{F}_t$ , and  $\mathcal{F}_0 = \mathcal{A}_G$ . There is an associated *vacuum expectation*  $\mathbb{E}_t : \mathcal{A}_G \otimes \mathcal{F} \rightarrow \mathcal{F}_t$  [29, Chapter 26] with respect to which the open dynamics satisfies

$$\mathbb{E}_s[X(t)] = X(s) + \int_s^t \mathbb{E}_s[\mathcal{G}_G(X(r))] dr \quad (22)$$

for all  $t \geq s$ . In this expression  $\mathbb{E}_s[X(t)]$  depends on the initial operators and the quantum noises up to time  $s$ , while the noises beyond time  $s$  have been averaged out; it captures the Markovian nature of the model.

### E. Quantum Feedback Networks

In this section we describe a quantum framework for feedback networks that will be used in the sequel, [12], [11]. *Quantum feedback networks* (QFN) consist of open quantum components that are interconnected by means of field channels that serve as “quantum wires”. These channels enable the directional transmission of quantum signals, thereby allowing the components to interact; the components may also interact directly via suitable couplings

that facilitate bidirectional energy exchanges, as discussed in section II-C. Here we focus on the directional interconnections. The QFN framework is expressed in terms of elementary constructs that enable efficient description of networks. These network constructs are defined in terms of the open system parameters  $(S, L, H)$  discussed in section II-D. As we will see, the framework generalizes the familiar transfer function descriptions widely used in classical linear systems theory; however, we emphasize that the QFN framework holds for general open quantum components whose dynamical variables may evolve nonlinearly (by this we mean that the differential equation for a component operator  $X(t)$  may be nonlinear).

QFN modeling proceeds as follows. Before implementing any connections, we first collect the components together. This is described using the concatenation product  $\boxplus$ , Figure 4. Next, we identify any series connections between components, which we describe using the series product  $\triangleleft$ , Figure 5. Networks that can be completely described using the concatenation and series products are called *reducible networks* (these were studied in detail in [12]). Any remaining signal connections will form part of a feedback loop that can be described in terms of a linear fractional transformation,  $F(G)$  [11]. All direct couplings between components can be accommodated using an interaction Hamiltonian of the form (13).

Suppose we are given two such systems:  $G_1 = (S_1, L_1, H)$  and  $G_2 = (S_2, L_2, H)$ , with physical variable spaces  $\mathcal{A}_{G_1}$  and  $\mathcal{A}_{G_2}$ , respectively. The products we define below combine these systems to produce new systems defined in terms of parameters drawn from the tensor product of variable spaces  $\mathcal{A}_{G_1} \otimes \mathcal{A}_{G_2}$ .

The *concatenation* of  $G_1$  and  $G_2$  is the system  $G_1 \boxplus G_2$  defined by

$$G_1 \boxplus G_2 = \left( \begin{pmatrix} S_1 & 0 \\ 0 & S_2 \end{pmatrix}, \begin{pmatrix} L_1 \\ L_2 \end{pmatrix}, H_1 + H_2 \right), \quad (23)$$

as illustrated in Figure 4 (where each arrowed line may represent multiple channels). It is possible to include zero-dimensional inputs into this scheme as a special case: if a system in isolation has no inputs then it is a closed dynamical system and its dynamics are described by a Hamiltonian  $H$ . It is convenient just to write this as  $G = (-, -, H)$  with the absence of inputs denoted by blanks; we then just set  $(-, -, H) \boxplus (-, -, H') := (-, -, H + H')$  and more generally  $(-, -, H) \boxplus (S', L', H') = (S', L', H') \boxplus (-, -, H) := (S', L', H + H')$ .




Fig. 4. Concatenation of two systems,  $G_1 \boxplus G_2$ .

Now suppose  $G_1 = (S_1, L_1, H)$  and  $G_2 = (S_2, L_2, H)$  have the same number of field channels (i.e.  $L_1$  and  $L_2$

have the same length). Then the *series product*  $G_2 \triangleleft G_1$  is defined by

$$G_2 \triangleleft G_1 = \left( S_2 S_1, L_2 + S_2 L_1, H_1 + H_2 + \text{Im}\{L_2^\dagger S_2 L_1\} \right), \quad (24)$$

see Figure 5.




Fig. 5. Series or cascade connection of two systems,  $G_2 \triangleleft G_1$ .

Several useful facts concerning the series product are the following: (i) given a system  $G = (S, L, H)$ , we have  $G = (I, L, H) \triangleleft (S, 0, 0) = (S, 0, 0) \triangleleft (I, S^\dagger L, H)$ , (ii) the inverse of a system  $G$  exists and is given by  $G^{-1} = (S^\dagger, -S^\dagger L, -H)$ , by which it is meant that  $G^{-1} \triangleleft G = G \triangleleft G^{-1} = I = (I, 0, 0)$ , and (iii) for any two systems  $G_1$  and  $G_2$  we have  $G_2 \triangleleft G_1 = G_1 \triangleleft \tilde{G}_2$  where  $\tilde{G}_2 = G_1^{-1} \triangleleft G_2 \triangleleft G_1 = (S_1^\dagger S_2 S_1, S_1^\dagger (S_2 - I) L_1 + S_1^\dagger L_2, H_2 + \text{Im}\{L_2^\dagger (S_2 + I) L_1 - L_1^\dagger S_2 L_1\})$ .

For future reference, we mention that the generators for the systems formed with the concatenation and series products are

$$\mathcal{G}_{G_1 \boxplus G_2}(X) = \mathcal{L}_{L_1}(X) + \mathcal{L}_{L_2}(X) - i[X, H_1 + H_2] = \mathcal{G}_{G_1}(X) + \mathcal{G}_{G_2}(X), \quad (25)$$

$$\begin{aligned} \mathcal{G}_{G_2 \triangleleft G_1}(X) &= \mathcal{L}_{L_2 + S_2 L_1}(X) - i[X, H_1 + H_2 + \frac{1}{2i}(L_2^\dagger S_2 L_1 - L_1^\dagger S_2^\dagger L_2)] \\ &= \mathcal{L}_{S_2 L_1}(X) + \mathcal{L}_{L_2}(X) + L_1^\dagger S_2^\dagger [X, L_2] + [L_2^\dagger, X] S_2 L_1 - i[X, H_1 + H_2] \\ &= \mathcal{L}_{L_1}(X) + \mathcal{L}_{L_2}(X) + L_1^\dagger (S_2^\dagger X S_2 - X) L_1 + L_1^\dagger S_2^\dagger [X, L_2] + [L_2^\dagger, X] S_2 L_1 - i[X, H_1 + H_2]. \end{aligned} \quad (26)$$

Next, consider a system  $G$  of the form

$$G = \left( \begin{pmatrix} S_{11} & S_{12} \\ S_{21} & S_{22} \end{pmatrix}, \begin{pmatrix} L_1 \\ L_2 \end{pmatrix}, H \right). \quad (27)$$

The feedback network  $F(G)$  defined by Figure 6 is well-defined provided  $I - S_{22}$  is invertible, in which case the parameters for  $F(G)$  are given by the linear fractional transformation [11]

$$\begin{aligned} F(G) &= (S_{11} + S_{12}(I - S_{22})^{-1} S_{21}, L_1 + S_{12}(I - S_{22})^{-1} L_2, \\ &H + \text{Im}\{L_1^\dagger S_{12}(I - S_{22})^{-1} L_2\} + \text{Im}\{L_2^\dagger S_{22}(I - S_{22})^{-1} L_2\}). \end{aligned} \quad (28)$$

*Remark 2.1:* Underlying the series and LFT network constructs is the simple idea of equating the input  $u_2$  with a slightly delayed version of the output  $y_2$ , and then letting the delay tend to zero. Full technical details are given in [10], [12], [11].  $\square$




Fig. 6. Quantum feedback network described by the linear fractional transformation  $F(G)$ .

### III. QUANTUM DISSIPATIVE SYSTEMS

We are now in a position to introduce a general definition of *dissipation* for open quantum systems. As we have indicated above, since dissipation concerns the loss of energy or coherence from a system of interest, which we call the *plant*, to an external environment, or the effect of an external system or environment on the system, we model the external influences as another open system, which we call an *exosystem*. Since we wish to consider the effect of a range of exosystems (analogous to a range of signal generators connected to an RLC circuit), we specify a class of allowed exosystems for the dissipation property. The definition, together with some examples, is presented in subsection III-A using the QFN framework from section II-E.

#### A. Definitions and Differential Characterization

A *plant*  $P$  is an open system of the type defined in subsection II-D:

$$P = (S, L, H). \quad (29)$$

It is the system of main interest, and is regarded as being part of a possibly larger network of systems. The space of physical variables for  $P$  is denoted  $\mathcal{S}_P$ . Since our interest is in modeling and analyzing the effect of the external influences on the plant, we assume that certain of its input and outputs are available for connection to an *exosystem*  $W$ , an open system

$$W = (R, w, D). \quad (30)$$

It is also assumed that certain plant variables are available for direct interconnection with an exosystem. Thus the plant definition and interconnection specification determine how it can interface with exosystems  $W$ , as discussed in subsection II-E. The interconnections determine a network  $P \wedge W$ , as shown in Figure 7 (a star product architecture, [13], [44], [11]). In terms of the network constructs of section II-E, we have explicitly

$$P \wedge W = F(G) \boxplus H_{PW}, \quad (31)$$

using the LFT (Figure 6), where

$$G = (I \boxplus J) \triangleleft (W \boxplus I) \triangleleft (I \boxplus P) \triangleleft (I \boxplus J), \quad (32)$$

as shown in Figure 8, and  $H_{PW}$  is a direct interaction Hamiltonian.

We will allow exosystems  $W$  to vary in a class  $\mathcal{W}$  of such exosystems. The operators constituting the system parameters  $W$  belong to an algebra  $\mathcal{A}_P \otimes \mathcal{A}_{ex}$ . The input to the system  $P \wedge W$  is assumed to be a canonical vacuum field.




Fig. 7. The plant-exosystem network  $P \wedge W$ .




Fig. 8. The system  $G$  used to represent the network  $P \wedge W$  of Figure 7.

Let  $r = r_P(W) \in \mathcal{A}_P \otimes \mathcal{A}_{ex}$  be a self-adjoint symmetrically ordered function of the exosystem parameters, depending on the plant parameters (e.g. a quadratic form), called a *supply rate*. In general, a supply rate may contain constant terms (see Example 3.10).

We say that the plant  $P$  is *dissipative* with supply rate  $r$  with respect to a class  $\mathcal{W}$  of exosystems if there exists a non-negative plant observable  $V \in \mathcal{A}_P$  such that

$$\mathbb{E}_0 \left[ V(t) - V - \int_0^t r(W)(s) ds \right] \leq 0 \quad (33)$$

for all exosystems  $W \in \mathcal{W}$  and all  $t \geq 0$ . Here, the dynamics is that of the network  $P \wedge W$ ,  $\mathbb{E}_0$  is the initial vacuum expectation onto  $\mathcal{A}_P \otimes \mathcal{A}_{ex}$  (which contains  $\mathcal{A}_P$ ), and  $\leq$  denotes operator ordering, see Appendix C.

We shall refer to (33) as the *dissipation inequality*. It is a natural generalization of Willems' definition [34] to open quantum systems, building on [6], [17]. Following the terminology from [34], when equality holds in (33) for all exosystems  $W \in \mathcal{W}$ , we say that the plant  $P$  is *lossless*. This terminology refers to the fact that in such cases

all energy flows and storages have been accounted for; the total system (plant, exosystem, fields) does not loose energy. Important special cases and applications of the dissipation inequality will be discussed below.

We next present the infinitesimal version of the dissipation inequality (33) in the following theorem.

*Theorem 3.1:* Let  $P$  be a plant, and  $P \wedge W$  be a given network structure for a class  $\mathcal{W}$  of exosystems. Then the plant  $P$  is *dissipative* with supply rate  $r$  with respect to  $\mathcal{W}$  if and only if there exists a non-negative system observable  $V \in \mathcal{A}_P$  such that

$$\mathcal{G}_{P \wedge W}(V) - r(W) \leq 0 \quad (34)$$

for all exosystem parameters  $W \in \mathcal{W}$ .

*Proof:* Assume  $P$  is dissipative as stated, and select any exosystem  $W \in \mathcal{W}$  and consider the plant-exosystem network  $P \wedge W$ . Now apply (22) to the network to obtain

$$\frac{d}{dt} \mathbb{E}_0[V(t)]|_{t=0} = \mathcal{G}_{P \wedge W}(V). \quad (35)$$

Now combine this with (33) to obtain (34). The converse follows by reversing this argument and integration. ■

Note that the dissipation inequality (34) involves only plant and exosystem operators, since the LHS depends on operators in the algebra  $\mathcal{A}_P \otimes \mathcal{A}_{ex}$  (the noise has been averaged out by  $\mathbb{E}_0$ ).

*Remark 3.2:* (Non-autonomous case.) For non-autonomous situations, the plant and exosystem operators may depend on time (they can even be random provided they are adapted), and the dissipation inequalities take the forms

$$\mathbb{E}_s \left[ V(t) - V(s) - \int_s^t r(W)(r) dr \right] \leq 0 \quad (36)$$

for all  $t \geq s$  and all exosystems  $W \in \mathcal{W}$ , and

$$\mathcal{G}_{P \wedge W}(V)(t) - r(W)(t) \leq 0 \quad (37)$$

for all  $t \geq 0$  and all exosystem parameters  $W \in \mathcal{W}$ . □

In general we can expect physical systems to be dissipative in some sense, and indeed we characterize this precisely in the next theorem. In what follows we denote by  $\mathcal{W}_u$  the class of exosystems without any particular constraints (unrestricted)—the only requirement is that members of  $\mathcal{W}_u$  are open systems that can be connected to the plant. The following simple (but important!) result follows from a calculation similar to that used to prove Theorem 3.1.

*Theorem 3.3:* Let  $P = (S, L, H)$  be a plant, and  $P \wedge W$  be a given network structure for the class  $\mathcal{W}_u$  of (unconstrained) exosystems. Assume there exists an observable  $V_0 \geq 0$  commuting with  $H$ . Then  $P$  is lossless (hence dissipative) with respect to  $\mathcal{W}_u$  for a supply rate  $r = r_0$  given by

$$r_0(W) = \mathcal{G}_{P \wedge W}(V_0), \quad (38)$$

with storage function  $V = V_0$ .

Theorems 3.1 and 3.3 are quite general, and contain many special cases of interest, e.g. versions of the Bounded and Positive Real Lemmas, as well as fundamental energy balance properties of physical systems. See Theorems 3.6 and 3.7 below.

It is instructive to examine the form of that “natural” supply rate  $r_0$  (defined by (38)) for the specific interconnection between the plant  $P = (I, L, H)$  and exosystems given by the series connection

$$P \wedge W = P \triangleleft W, \quad (39)$$

and where the Hamiltonian  $D$  of the exosystem has the form

$$D = -i(K^\dagger v - v^\dagger K), \quad (40)$$

where  $K \in \mathcal{A}_P$  is fixed and  $v$  commutes with  $\mathcal{A}_P$ . Then we have

$$\begin{aligned} r_0(W) &= r_0(w, v) = \mathcal{L}_w(V_0) + \mathcal{L}_L(V_0) + w^\dagger[V_0, L] + [L^\dagger, V_0]w - i[V_0, D] \\ &= \mathcal{L}_w(V_0) + \mathcal{L}_L(V_0) + \begin{pmatrix} w^\dagger & v^\dagger \end{pmatrix} [V_0, \begin{pmatrix} L \\ K \end{pmatrix}] + [\begin{pmatrix} L^\dagger & K^\dagger \end{pmatrix}, V_0] \begin{pmatrix} w \\ v \end{pmatrix} \\ &= \mathcal{L}_w(V_0) + \mathcal{L}_L(V_0) + \begin{pmatrix} w^\dagger & v^\dagger \end{pmatrix} Z + Z^\dagger \begin{pmatrix} w \\ v \end{pmatrix}, \end{aligned} \quad (41)$$

where

$$Z = [V_0, \begin{pmatrix} L \\ K \end{pmatrix}]. \quad (42)$$

This means that the plant  $P = (I, L, H)$  satisfies the lossless energy rate relation

$$\mathcal{G}_{P \triangleleft W}(V_0) = \mathcal{L}_w(V_0) + \mathcal{L}_L(V_0) + \begin{pmatrix} w^\dagger & v^\dagger \end{pmatrix} Z + Z^\dagger \begin{pmatrix} w \\ v \end{pmatrix}. \quad (43)$$

This relation may be regarded as a generalization of the well-known passivity relation for classical Hamiltonian systems (see, e.g. [32, eq. (2.39) and Chapter 4]).<sup>1</sup> If we think of  $Z$  as an “output” quantity (not necessarily part of an output field channel!), then the last two terms correspond to a product of input and output terms, i.e. an energy flow into the plant from the exosystem—these terms capture the *passivity* of the plant, as we now explain. The term  $\mathcal{L}_L(V_0)$  is known in quantum physics as a “dissipation” or “damping” term, which in the model arises from the quantum noise in the field; when negative, this term represents energy lost from the plant to the field (heat bath). The first term,  $\mathcal{L}_w(V_0)$ , arises from a “ $dt$ ” or “signal” term in the field inputs, and is in general zero when  $w$  commutes with plant operators; it is an exosystem partner to the field dissipation term. Indeed, if we integrate (43) and take expectations with respect to a joint state consisting of a plant state vector  $\psi_0$  for which  $\langle \psi_0, V_0 \psi_0 \rangle = 0$

<sup>1</sup>For a classical Hamiltonian system with Hamiltonian  $H = H_0 + Gu$ , we have  $dH_0/dt = \{H_0, H\} = zu$ , where  $u$  is an input and  $z = \{H_0, G\}$  is an output (here the Poisson bracket is defined by  $\{f, g\} = \nabla^T f \Sigma \nabla g$ , where  $\Sigma = \begin{pmatrix} 0 & 1 \\ -1 & 0 \end{pmatrix}$ ).

and the vacuum state for the network input fields, we find that

$$\int_0^t \langle \mathcal{L}_w(V_0)(s) + \mathcal{L}_L(V_0)(s) + \begin{pmatrix} w^\dagger(s) & v^\dagger(s) \end{pmatrix} Z(s) + Z^\dagger(s) \begin{pmatrix} w(s) \\ v(s) \end{pmatrix} \rangle ds \geq 0, \quad (44)$$

which generalizes well known passivity inequalities. Passivity and gain will be discussed in more detail in section III-C, which also contains illustrative examples.

### B. Stability

In the case of classical deterministic systems, dissipativity plays an important role in stability analysis, [34], [14]. For instance, strictly passive systems are asymptotically stable. The purpose of this section is to make this connection in our current quantum context using a simple exponential stability criterion, given in the following lemma.

*Lemma 3.4:* Let  $P$  be a plant for which there exists a non-negative observable  $V$  satisfying the differential inequality

$$\mathcal{G}_P(V) + cV \leq \lambda, \quad (45)$$

where  $c > 0$  and  $\lambda$  are real numbers. Then for any plant state we have

$$\langle V(t) \rangle \leq e^{-ct} \langle V \rangle + \lambda/c. \quad (46)$$

Moreover, if  $\lambda = 0$  then  $\lim_{t \rightarrow \infty} \langle V(t) \rangle = 0$ .

*Proof:* Integrating the plant dynamics we find that

$$\mathbb{E}_t \left[ V(t+h) - V(t) - c \int_t^{t+h} V(r) dr \right] \leq \lambda h, \quad (h \geq 0). \quad (47)$$

Now from [29, sec. 26], we have  $\mathbb{E}_0 \mathbb{E}_t = \mathbb{E}_0$  for  $t \geq 0$ , hence it follows that the expectation  $\langle V(t) \rangle = \langle \psi, \mathbb{E}_0[V(t)] \psi \rangle$  ( $\psi$  is the plant state) satisfies

$$\langle V(t+h) \rangle - \langle V(t) \rangle - c \int_t^{t+h} \langle V(r) \rangle dr \leq \lambda h, \quad (h \geq 0). \quad (48)$$

From this we deduce

$$\frac{d}{dt} \langle V(t) \rangle \leq -c \langle V(t) \rangle + \lambda. \quad (49)$$

The assertions of the lemma now follow. ■

We now state a stability result for strictly dissipative systems.

*Theorem 3.5:* Let  $P$  be dissipative with storage function  $V$  and supply rate  $r(W)$ . Assume that the supply rate satisfies

$$r(I) \leq -cV \quad (50)$$

for some real number  $c > 0$ . Then for the unperturbed plant  $P = P \triangleleft I$  we have  $\lim_{t \rightarrow \infty} \langle V(t) \rangle = 0$  for any plant state.

This result follows, of course, from Lemma 3.4 and Theorem 3.1. It is possible to consider more general stability results and this will be taken up in future work.



### C. Passivity and Gain

In this subsection we consider passivity and gain properties for the series plant-exosystem interconnection, (39). In particular, we present generalizations of the positive and bounded real lemmas (Theorems 3.6 and 3.7 below). To help make the ideas clearer, we will assume that the exosystems commute with the plant. More general results can be formulated using the framework developed in this paper.

Consider a plant  $P = (I, L, H)$ , and let  $N, Z \in \mathcal{A}_P$ . Define a class of exosystems

$$\mathcal{W}_1 = \{W = (R, w, -i(K^\dagger v - v^\dagger K)) : K \in \mathcal{A}_P \text{ is fixed and } w, v \text{ commute with } \mathcal{A}_P\}.$$

We say that  $P$  is *passive* (with respect to  $\mathcal{W}_1$ ) if it is dissipative with respect to the supply rate

$$r(W) = r(w, v) = -N^\dagger N + \begin{pmatrix} w^\dagger & v^\dagger \end{pmatrix} Z + Z^\dagger \begin{pmatrix} w \\ v \end{pmatrix} + \lambda \quad (51)$$

for some non-negative real number  $\lambda$ . Explicitly, this means that  $P$  is passive if there exists a non-negative system observable  $V \in \mathcal{A}_P$  and a non-negative real number  $\lambda$  such that

$$\mathbb{E}_0 \left[ V(t) - V - \int_0^t \left( \begin{pmatrix} w^\dagger(s) \\ v^\dagger(s) \end{pmatrix} Z(s) + Z^\dagger(s) \begin{pmatrix} w(s) & v(s) \end{pmatrix} - N^\dagger(s)N(s) \right) ds \right] - \lambda t \leq 0 \quad (52)$$

for all exosystems  $W \in \mathcal{W}_1$  and all  $t \geq 0$ .

**Theorem 3.6:** (Positive Real Lemma) A plant  $P = (I, L, H)$  is passive (with respect to  $\mathcal{W}_1$ ) if and only if there exists a non-negative system observable  $V \in \mathcal{A}_P$  and a non-negative real number  $\lambda$  such that

$$\mathcal{L}_L(V) - i[V, H] + N^\dagger N - \lambda \leq 0, \quad (53)$$

$$Z = [V, \begin{pmatrix} L \\ K \end{pmatrix}]. \quad (54)$$

*Proof:* We use some results from the Appendix in what follows. If  $P$  is passive, there exists a non-negative system observable  $V \in \mathcal{A}_P$  and a non-negative real number  $\lambda$  such that

$$\mathcal{L}_L(V) - i[V, H] + \begin{pmatrix} w^\dagger \\ v^\dagger \end{pmatrix} ([V, L] - Z) + ([L^\dagger, V] - Z^\dagger) \begin{pmatrix} w & v \end{pmatrix} + N^\dagger N - \lambda \leq 0 \quad (55)$$

for all exosystem parameters  $W = (R, w, -i(v^\dagger K - K^\dagger v)) \in \mathcal{W}_1$ . Setting  $w = 0$  and  $v = 0$  we obtain (53). Now let  $w$  vary freely but commuting with plant operators to deduce (54). ■

The Bounded Real Lemma is used to determine the  $L^2$  gain of a system, and in conjunction with the Small Gain Theorem, can be used for robust stability analysis and design, [13], [44], [4]. Again consider a plant  $P = (1, L, H)$ , let  $N, Z \in \mathcal{A}_P$ , and let  $g > 0$  be a real number (gain parameter). In order to simplify the exposition, we restrict our attention to the class

$$\mathcal{W}_2 = \{W = (R, w, 0) : w \text{ commutes with } \mathcal{A}_P\}.$$

We say that  $P$  has *gain*  $g$  (with respect to  $\mathcal{W}_2$ ) if it is dissipative with respect to the supply rate

$$r(W) = g^2 w^\dagger w - (N + Zw)^\dagger (N + Zw) + \lambda, \quad (56)$$

for a real number  $\lambda \geq 0$ , and class  $\mathcal{W}_2$ ; i.e. there exists a non-negative system observable  $V \in \mathcal{A}_P$  and a non-negative real number  $\lambda$  such that

$$\mathbb{E}_0 \left[ V(t) - V - \int_0^t (g^2 w^\dagger(s) w(s) - (N(s) + Z(s)w(s))^\dagger (N(s) + Z(s)w(s))) ds \right] - \lambda t \leq 0 \quad (57)$$

for all exosystems  $W \in \mathcal{W}_2$  and all  $t \geq 0$ .

*Theorem 3.7:* (Bounded Real Lemma) A plant  $P = (I, L, H)$  has gain  $g$  (with respect to  $\mathcal{W}_2$ ) if and only if there exists a non-negative system observable  $V \in \mathcal{A}_P$  and a non-negative real number  $\lambda$  such that

$$\Gamma = g^2 - Z^\dagger Z \geq 0 \quad (58)$$

and

$$\mathcal{L}_L(V) - i[V, H] - w^\dagger \Gamma w + w^\dagger ([V, L] + Z^\dagger N) + ([V, L] + Z^\dagger N)^\dagger w + N^\dagger N - \lambda \leq 0 \quad (59)$$

for all exosystem parameters  $w$ . If  $\Gamma^{-1}$  exists, then  $P = (1, L, H)$  has gain  $g$  (with respect to  $\mathcal{W}_2$ ) if

$$\mathcal{L}_L(V) - i[V, H] + N^\dagger N + ([L^\dagger, V] + N^\dagger Z) \Gamma^{-1} ([V, L] + Z^\dagger N) - \lambda \leq 0. \quad (60)$$

*Proof:* If  $P$  has gain  $g$ , then there exists a non-negative system observable  $V \in \mathcal{A}_P$  and a real number  $\lambda \geq 0$  such that

$$\mathcal{L}_L(V) - i[V, H] - w^\dagger \Gamma w + w^\dagger ([V, L] + Z^\dagger N) + ([V, L] + Z^\dagger N)^\dagger w + N^\dagger N - \lambda \leq 0 \quad (61)$$

for all exosystem parameters  $w$ . From the Appendix we see that  $\Gamma \geq 0$ , hence (58). In equality (59) also follows.

Next, if  $\Gamma^{-1}$  exists, define

$$w^* = \Gamma^{-1} ([V, L] + Z^\dagger N). \quad (62)$$

Then by completion of squares

$$\begin{aligned} & -w^\dagger \Gamma w + w^\dagger ([V, L] + Z^\dagger N) + ([L^\dagger, V] + N^\dagger Z) w \\ &= ([L^\dagger, V] + N^\dagger Z) \Gamma^{-1} ([V, L] + Z^\dagger N) - (w - w^*)^\dagger \Gamma (w - w^*) \\ &\leq ([L^\dagger, V] + N^\dagger Z) \Gamma^{-1} ([V, L] + Z^\dagger N). \end{aligned}$$

This inequality and (60) imply (59) as required.  $\blacksquare$

*Remark 3.8:* Note that the “optimal” exosystem parameter  $w^*$  defined by (62) belongs to  $\mathcal{A}_P$ , and so does not in general commute with  $\mathcal{A}_P$ , and consequently lies outside the class of exosystems under consideration; i.e.,  $w^* \notin \mathcal{W}_2$  in general.  $\square$

We conclude this section with several examples. The first example is that of a two-level system, Appendix A.

*Example 3.9:* (Two-level atom) In this example we consider an open two level atom

$$P = (1, \sqrt{\gamma} \sigma_-, \frac{1}{2} \omega \sigma_z),$$

where  $\sigma_x, \sigma_y, \sigma_z$  denote the Pauli matrices (Appendix A) and  $\sigma_\pm = \frac{1}{2}(\sigma_x \pm i\sigma_y)$ .

Consider the storage function  $V_0 = \sigma_1 = \frac{1}{2}(I + \sigma_z) \geq 0$  (here  $I$  is the  $2 \times 2$  identity matrix). Then by (41) we have

$$\begin{aligned} r_0(W) &= -\gamma\sigma_1 - \sqrt{\gamma}(w^*\sigma_- + \sigma_+w) + \mathcal{L}_w(\sigma_1) - i[\sigma_1, D] \\ &= -(\sqrt{\gamma}\sigma_- + w)^*(\sqrt{\gamma}\sigma_- + w) + w^*w + \mathcal{L}_w(\sigma_1) - i[\sigma_1, D]. \end{aligned} \quad (63)$$

Therefore this system is lossless (passive), and has gain 1 with respect to the output quantity  $\sqrt{\gamma}\sigma_- + w$  and commuting inputs  $w$ . When  $D = 0$  and  $W = (1, 0, 0)$ , then by Theorem 3.5 the expected value of  $V_0(t) = \sigma_1(t)$  tends to zero (asymptotically stable).  $\square$

The next example looks at open quantum oscillators, Appendix B.

*Example 3.10:* (Open Oscillator) Consider the plant

$$P = (1, \alpha a + \beta a^*, \omega a^* a),$$

where  $a$  is the annihilation operator (satisfying the commutation relations  $[a, a^*] = 1$ , recall Appendix B),  $\alpha$  and  $\beta$  are complex numbers, and  $\omega$  is a frequency parameter. The case  $\alpha = \sqrt{\gamma}$ ,  $\beta = 0$  corresponds to a damped cavity with coupling  $L = \sqrt{\gamma}a$ , while the undamped oscillator model for an atom using in [5] has coupling  $L = \sqrt{\kappa}(a + a^*)$  for which  $\alpha = \beta = \sqrt{\kappa}$ . The coupling  $L = a^*$  arises in amplifier models, [10].

With  $V_0 = a^*a$  and  $W = (1, w, 0)$ , from (41) we have

$$r_0(W) = \mathcal{L}_w(V_0) + (|\beta|^2 - |\alpha|^2)V_0 + w^*Z + Z^*w + |\beta|^2, \quad (64)$$

where  $Z = -\alpha a + \beta a^*$ . From this it can be seen that  $P$  is passive whenever  $|\beta|^2 - |\alpha|^2 \leq 0$ . Furthermore, if  $|\beta|^2 - |\alpha|^2 < 0$  (strict passivity) and  $W = (1, 0, 0)$  it follows from Lemma 3.4 that the plant is stable, i.e. the expected value of  $V_0$  remains bounded. If in addition  $\beta = 0$  then the expected value of  $V_0$  tends to zero.

In the strictly passive case we may complete the squares to deduce that the plant has finite gain. For instance, if  $\alpha = \sqrt{\gamma}$ ,  $\beta = 0$  (damped cavity) we have

$$r_0(W) = -(\sqrt{\gamma}a + w)^*(\sqrt{\gamma}a + w) + w^*w + \mathcal{L}_w(V_0) \quad (65)$$

and hence the system has gain 1 relative to the output quantity  $\sqrt{\gamma}a + w$  and commuting inputs  $w$ .

If  $|\beta|^2 - |\alpha|^2 > 0$ , the plant is not passive and not stable. The case  $|\beta|^2 - |\alpha|^2 = 0$  is marginally stable.  $\square$

The final example of this section concerns classical deterministic systems, of which the RLC circuit discussed earlier is a special case (see section II-A).

*Example 3.11:* (classical deterministic systems) Consider the classical deterministic open system (see [34], [32])

$$\begin{aligned} \dot{x} &= f(x) + g(x)w \\ z &= h(x), \end{aligned} \quad (66)$$

where  $x \in \mathbb{R}^n$ ,  $w \in L_{loc}^2([0, \infty), W)$ ,  $W \subset \mathbb{R}$ ,  $f$  and  $g$  are smooth vector fields, and  $h$  is a smooth real-valued function. This system is dissipative with respect to a supply rate  $r(w, z)$  if there exists a non-negative function (the

storage function) such that

$$V(x(t)) - V(x(0)) - \int_0^t r(w(s), z(s)) ds \leq 0 \quad (67)$$

for all  $w \in L^2[0, t]$  and all  $t \geq 0$ . The infinitesimal version of this dissipation inequality is

$$\sup_{w \in W} \{[f(x) + g(x)w]^T \nabla V(x) - r(w, h(x))\} \leq 0. \quad (68)$$

This is a special case of the quantum formulation given above. To see this, we represent the classical open system as a commutative subsystem of a quantum open system  $P$  with an associated (non-autonomous) exosystem class  $\mathcal{W}$ . As in [12, Appendix B], we take the underlying Hilbert space of the classical system to be  $H = L^2(\mathbb{R}^n)$  with  $q^j$ ,  $p_j$  being the usual canonical position and momentum observables:  $q^j \psi(x) = x^j \psi(x)$  and  $p_j \psi(x) = -i \partial_j \psi(x)$ . We write  $q = (q^1, \dots, q^n)^T$ ,  $p = (p_1, \dots, p_n)^T$ , and  $\nabla = (\partial_1, \dots, \partial_n)^T$ , and define Hamiltonians

$$H_f = \frac{1}{2} (f^T p + p^T f), \quad H_g = \frac{1}{2} (g^T p + p^T g). \quad (69)$$

Now if  $\varphi = \varphi(q)$  is a function only of the position variables, then

$$-i[\varphi, H_f + H_g w] = [f + gw]^T \nabla \varphi. \quad (70)$$

Hence the classical open system can be described by  $P \boxplus W$ , where

$$\begin{aligned} P &= (-, -, H_f), \\ W &\in \mathcal{W} = \{W = (-, -, H_g w) : w \in L_{loc}^2([0, \infty), W)\}, \end{aligned} \quad (71)$$

and supply rate

$$r(W) = r(h, w). \quad (72)$$

The classical deterministic dissipation inequality (68) now follows from (34). In a similar way, one can also represent classical open stochastic systems, though we do not do so here.  $\square$

#### D. Dissipative Networks

Dissipation properties for QFNs can be analyzed by considering how the network is constructed in terms of the elementary constructs (concatenation, series connection, direct interaction, LFT) and knowledge of how dissipation “transforms” under these constructs. This is the purpose of the following results. The first lemma considers concatenation and series connections.

*Lemma 3.12:* Let  $P_1$  and  $P_2$  be given plants and  $P_1 \wedge W_1$  and  $P_2 \wedge W_2$  are network structures to be specified. Assume  $P_1$  and  $P_2$  are dissipative with respect to supply rates  $r_{P_1}(W_1)$  and  $r_{P_2}(W_2)$ , storage functions  $V_1$  and  $V_2$ , and exosystem classes  $\mathcal{W}_1$  and  $\mathcal{W}_2$  respectively. Then:

- 1) If  $P_1 \wedge W_1 = P_1 \boxplus W_1$  and  $P_2 \wedge W_2 = P_2 \boxplus W_2$ , then the network  $P_1 \boxplus P_2$  is dissipative with respect to the network structure  $(P_1 \boxplus P_2) \triangleleft W$  and exosystem class  $\mathcal{W}_1 \boxplus \mathcal{W}_2$ ; the storage function is  $V = V_1 + V_2$  and the supply rate is

$$r_{P_1 \boxplus P_2}(W_1 \boxplus W_2) = r_{P_1}(W_1) + r_{P_2}(W_2) + \mathcal{G}_{P_1 \triangleleft W_1}(V_2) + \mathcal{G}_{P_2 \triangleleft W_2}(V_1). \quad (73)$$

If  $V_1$  commutes with  $\mathcal{A}_{P_2}$  and  $\mathcal{W}_2$  and if  $V_2$  commutes with  $\mathcal{A}_{P_1}$  and  $\mathcal{W}_1$ , then the supply rate is simply the sum of the supply rates:  $r_{P_1 \boxplus P_2}(W_1 \boxplus W_2) = r_{P_1}(W_1) + r_{P_2}(W_2)$ .

- 2) If  $P_1 \wedge W_1 = P_1 \triangleleft W_1$  and  $P_2 \wedge W_2 = P_2 \triangleleft W_2$ , then the network  $P_2 \triangleleft P_1$  is dissipative with respect to the network structure  $P_2 \triangleleft P_1 \triangleleft W$  and exosystem class

$$\mathcal{W} = \{W : P'_2 \triangleleft W \in \mathcal{W}_1 \text{ and } P_1 \triangleleft W \in \mathcal{W}_2\}, \quad (74)$$

where  $P'_2 = P_1^{-1} \triangleleft P_2 \triangleleft P_1 = (S_1^\dagger S_2 S_1, S_1^\dagger (S_2 - I)L_1 + S_1^\dagger L_2, H_2 + \text{Im}\{L_2^\dagger (S_2 + I)L_1 - L_1^\dagger S_2 L_1\})$ ; the storage function is  $V = V_1 + V_2$  and the supply rate is

$$r_{P_2 \triangleleft P_1}(W) = r_{P_1}(P'_2 \triangleleft W) + r_{P_2}(P_1 \triangleleft W). \quad (75)$$

*Proof:* For part 1, we have

$$\begin{aligned} \mathcal{G}_{(P_1 \boxplus P_2) \triangleleft (W_1 \boxplus W_2)}(V_1 + V_2) &= \mathcal{G}_{(P_1 \triangleleft W_1) \boxplus (P_2 \triangleleft W_2)}(V_1 + V_2) \\ &= \mathcal{G}_{P_1 \triangleleft W_1}(V_1) + \mathcal{G}_{P_2 \triangleleft W_2}(V_2) + \mathcal{G}_{P_1 \triangleleft W_1}(V_2) + \mathcal{G}_{P_2 \triangleleft W_2}(V_1) \\ &\leq r_{P_1}(W_1) + r_{P_2}(W_2) + \mathcal{G}_{P_1 \triangleleft W_1}(V_2) + \mathcal{G}_{P_2 \triangleleft W_2}(V_1), \end{aligned}$$

so that the last line is a supply rate for the concatenated system.

Similarly, for part 2 we have

$$\begin{aligned} \mathcal{G}_{P_2 \triangleleft P_1 \triangleleft W}(V_1 + V_2) &= \mathcal{G}_{P_2 \triangleleft P_1 \triangleleft W}(V_1) + \mathcal{G}_{P_2 \triangleleft P_1 \triangleleft W}(V_2) \\ &= \mathcal{G}_{P_1 \triangleleft (P'_2 \triangleleft W)}(V_1) + \mathcal{G}_{P_2 \triangleleft (P_1 \triangleleft W)}(V_2) \\ &\leq r_{P_1}(P'_2 \triangleleft W) + r_{P_2}(P_1 \triangleleft W) \end{aligned}$$

where  $P'_2 = P_1^{-1} \triangleleft P_2 \triangleleft P_1 = (S_1^\dagger S_2 S_1, S_1^\dagger (S_2 - I)L_1 + S_1^\dagger L_2, H_2 + \text{Im}\{L_2^\dagger (S_2 + I)L_1 - L_1^\dagger S_2 L_1\})$  ([12, Theorem 3.4]). ■

In the next lemma, we consider the dissipation properties of a LFT feedback system in terms of series plant-exosystem network structures.

*Lemma 3.13:* Let  $P$  be a plant of the form (27) that is dissipative with supply rate  $r(W)$  and storage function  $V$  with respect to the network structure  $P \triangleleft W$  and exosystem class  $\mathcal{W}$ . Assume the LFT system  $F(P)$  is well-defined (Figure 6, section II-E). Define a class

$$F(\mathcal{W}) = \{(1, w, 0) : (1, w, 0) \boxplus (1, (I - S_{22})^{-1}(S_{21}w + L_2), 0) \in \mathcal{W}\}$$

Then  $F(P)$  is dissipative with storage function  $V$  and supply rate

$$r_{F(P)}(W) = r_P((1, w, 0) \boxplus (1, (I - S_{22})^{-1}(S_{21}w + L_2), 0)) \quad (76)$$

for  $W = (1, w, 0) \in F(\mathcal{W})$  relative to the network structure  $F(P) \triangleleft W$ .

*Proof:* Let  $W = (1, w, 0) \in F(\mathcal{W})$ , and consider the system  $F(P) \triangleleft W$ . By elimination of the internal signal in the feedback loop, we see that

$$\tilde{W} = (1, w, 0) \boxplus (1, (I - S_{22})^{-1}(S_{21}w + L_2), 0)$$

is an admissible exosystem for  $P$ . The result now follows from the assumed dissipation property for  $P$ . ■

The next lemma describes how series architectures may be used to modify the plant and supply rates.

*Lemma 3.14:* Let  $P$  and  $Q$  be systems for which the series connection  $P \triangleleft Q$  is well defined, and assume

$$W \in \mathcal{W} \text{ implies } Q \triangleleft W \text{ and } Q^{-1} \triangleleft W \in \mathcal{W}. \quad (77)$$

Then the plant  $P$  is dissipative with storage function  $V$  and supply rate  $r_P(W)$  with respect to  $\mathcal{W}$  and series network architecture  $P \triangleleft W$  if and only if the plant  $P \triangleleft Q$  is dissipative with storage function  $V$  and supply rate  $r_P(Q \triangleleft W)$  with respect to  $\mathcal{W}$  and series network architecture  $P \triangleleft Q \triangleleft W$ .

*Proof:* The assertions follow from the relation

$$\mathcal{G}_{P \triangleleft Q \triangleleft W}(V) = r_P(Q \triangleleft W).$$

As a consequence of Lemma 3.14, the scattering matrix  $S$  for the plant can be moved into the supply rate.

*Corollary 3.15:* Let  $\mathcal{W}$  be a class of exosystems satisfying

$$W \in \mathcal{W} \text{ implies } (S, 0, 0) \triangleleft W \text{ and } (S^\dagger, 0, 0) \triangleleft W \in \mathcal{W}. \quad (78)$$

Then:

- 1) The plant  $P = (S, L, H)$  is dissipative with supply rate  $r(W)$  with respect to  $\mathcal{W}$  series architecture  $P \triangleleft W$  if and only if the plant  $P' = (1, L, H)$  is dissipative with supply rate  $r'(W) = r((S^\dagger, 0, 0) \triangleleft W)$  with respect to  $\mathcal{W}$  and series architecture  $P' \triangleleft W$ .
- 2) The plant  $P = (I, L, H)$  is dissipative with supply rate  $r(W)$  with respect to  $\mathcal{W}$  series architecture  $P \triangleleft W$  if and only if the plant  $P' = (S, L, H)$  is dissipative with supply rate  $r'(W) = r((S, 0, 0) \triangleleft W)$  with respect to  $\mathcal{W}$  and series architecture  $P' \triangleleft W$ .

The following example illustrates the use of some of the above results by considering the dissipation properties of a network analogous to [34, Fig. 1 and Theorem 5, sec. 4].

*Example 3.16:* Consider a network  $N$  consisting of  $n$  plants  $P_1, \dots, P_n$  interconnected via field channels and a static connection system  $T$  (with complex numerical entries), Figure 9. In terms of the notation of this paper,  $N = F(P)$ , where  $P = \tilde{P} \triangleleft (I \boxplus \tilde{T})$ ,  $\tilde{P} = Q_2 \triangleleft (P_1 \boxplus \dots \boxplus P_n) \triangleleft Q_1$ , and  $\tilde{T} = Q_4 \triangleleft T \triangleleft Q_3$ . Here,  $Q_1, Q_2, Q_3, Q_4$  are appropriately sized permutation matrices (static components that interchange signals).

We assume that the network  $N$  of Figure 9 is well-defined and that for  $j = 1, \dots, n$  let  $P_j = (I, L_j, H_j)$  be dissipative systems with supply rates  $r_j(\tilde{W}_j)$  and storage functions  $V_j$  with respect to the network structures  $P_j \triangleleft \tilde{W}_j$  and exosystem classes  $\mathcal{W}_j$ . Since the network  $N = F(P)$  has  $n$  input channels corresponding to the channels not involved in the interconnection, we may consider a series architecture  $N \triangleleft W$ , where  $W = \boxplus_j W_j$  with appropriately sized exosystems of the form  $W_j = (1, w_j, 0)$ . Then we can see that with respect to the network structure  $N \triangleleft W$  the network  $N$  is dissipative with storage function  $V = V_1 + \dots + V_n$  as follows.




Fig. 9. (a) Quantum network  $N$  formed by interconnecting systems with a static connection system  $T$  ([34, Fig. 1]). (b) Equivalent representation of the network  $N = F(\tilde{P} \triangleleft (I \boxplus \tilde{T}))$ .

First, by the first part of Lemma 3.12, we know that  $\boxplus_j P_j$  is dissipative with storage function  $V$  and supply rate

$$r_{\boxplus_j P_j}(\boxplus_j \tilde{W}_j) = \sum_j r_{P_j}(\tilde{W}_j)$$

with respect to the network structure  $(\boxplus_j P_j) \triangleleft (\boxplus_j \tilde{W}_j)$ , where  $\tilde{W}_j \in \mathcal{W}_j$ . Next, we write  $P = R \triangleleft S$  where

$$R = Q_2 \triangleleft (\boxplus_j P_j) = \boxplus_j R_j, \quad S = Q_1 \triangleleft (I \boxplus (Q_4 \triangleleft T \triangleleft Q_3)),$$

and  $R_j = (I, L_{\pi_2(j)}, 0)$ . Here  $\pi_2$  is the permutation corresponding to  $Q_2$ . Now  $R$  is simply a re-arrangement of  $\boxplus_j P_j$ , and so it is dissipative with supply rate

$$r_R(\tilde{W}) = \sum_j r_{P_{\pi_2(j)}}(\tilde{W}_j),$$

where  $\tilde{W} = \boxplus_j \tilde{W}_j$ , storage function  $V$  and series architecture.

Write  $\hat{W} = \boxplus_j \hat{W}_j = \boxplus_j (I, \hat{w}_j, 0)$  and  $\tilde{W} = S \triangleleft \hat{W} = (1, S\hat{w}, 0)$ . Then  $P = R \triangleleft S$  is dissipative with respect to the series structure  $P \triangleleft \hat{W}$  with supply rate

$$r_P(\hat{W}) = r_R(\tilde{W}) = \sum_j r_{P_{\pi_2(j)}}\left(\sum_k S_{jk} w_k\right).$$

The supply rate for the network  $N = F(P)$  now follows from Lemma 3.13. The exosystem class can be determined from these calculations.  $\square$

### E. Uncertainty Modeling

Because of its importance to questions of robustness, in this subsection we briefly discuss how uncertainty can be modeled in the framework of this paper. However, a detailed treatment of robustness is beyond the scope of the present paper. The plant-exosystem network architecture  $P \wedge W$  illustrated in Figure 7 together with a specification of exosystem class  $\mathcal{W}$  provides a general scheme capable of accommodating a wide range of uncertainty models. Here for definiteness we set  $P \wedge W = P \triangleleft W$ , and consider a simple but common situation of parameter uncertainty.

Consider a plant  $P = (I, L, H)$ , where

$$L = (1 + \epsilon)L_0, \quad H = H_0 + D. \quad (79)$$

Here  $\epsilon$  is a real parameter. Then using (24) we can write

$$P = P_0 \triangleleft W = (I, L_0, H) \triangleleft (I, \epsilon L_0, D), \quad (80)$$

which represents the plant  $P$  as a nominal system  $P_0$  with the uncertainty connected into it from an exosystem  $W$  containing the uncertainty terms. Note that  $P$  and  $W$  are not independent systems, and in fact share variables.

The following example looks at the effect of parameter uncertainty on the behavior of the damped oscillator (recall Example 3.10).

*Example 3.17: (Parameter uncertainty)* As an example of this type of uncertainty modeling, consider the plant of Example 3.10, where  $\alpha = \sqrt{\gamma}$ , and  $\beta = 0$  (damped oscillator). Uncertainty arises from the parameter values  $\gamma$  and  $\omega$ , which may not be known accurately. This type of uncertainty is common in quantum optics, where  $\gamma$  is a measure of mirror transmissivity and  $\omega$  corresponds to a detuning of the cavity relative to the input field. In the above notation, let  $L_0 = \sqrt{\gamma_0} a$ ,  $H_0 = 0$  denote the nominal parameters, defining the nominal plant  $P_0 = (1, \sqrt{\gamma_0} a, 0)$ , a tuned cavity. Let the true parameters be  $L = (1 + \epsilon)\sqrt{\gamma_0} a$ ,  $H = \omega a^* a$ , a detuned cavity  $P = (1, (1 + \epsilon)\sqrt{\gamma_0} a, \omega a^* a)$ . Hence the uncertain exosystem is  $W = (1, \epsilon\sqrt{\gamma_0} a, \omega a^* a)$  (so that  $w = \epsilon\sqrt{\gamma_0} a$  and  $D = \omega a^* a$ ).

Then a straightforward calculation using (18) shows that

$$\begin{aligned} \mathcal{G}_P(a^* a) &= \mathcal{G}_{P_0}(a^* a) - (\epsilon^2 + 2\epsilon)\gamma_0 a^* a \\ &= -(1 + \epsilon)^2 a^* a \leq 0. \end{aligned}$$

This means that the true system is always stable, regardless of the uncertainty, though the decay rate does change. This of course is expected of a passive physical system.

However, other aspects of system performance may be affected. For instance, consider the quadratures  $q = a + a^*$ ,  $p = -i(a - a^*)$ , which are rotated by the detuning  $\omega$ . Indeed, if we focus on the observable  $q^2$ , then the uncertain exosystem contribution to the true generator (recall (18)) is

$$-i[q^2, \omega a^* a] = \omega(qp + pq),$$

which depends on the detuning parameter  $\omega$ . We see, therefore, that a detailed robustness analysis with respect to parameter uncertainty may involve consideration of one or more physical variables.  $\square$

#### IV. FEEDBACK CONTROL DESIGN BY INTERCONNECTION

##### A. Control Design Formulation

In the previous section we described how the behavior of plant is influenced by exogenous influences (represented as exosystems) using a quantum network framework. We now employ this same framework to consider problems of control system design. The network framework allows us to efficiently express a range of control design problems.



Indeed, in what follows we describe a control design procedure that extends classical methods including passivity-based control (PBC), “energy shaping” control, interconnection and damping assignment (IDA) PBC, and “control as interconnection”, [26], [32], [27], [28], [35], [36], [31], [30], [38].

Let  $P$  be a plant which can be interconnected with a controller  $C$  and an exosystem  $W$  in a network  $P \wedge C \wedge W$ , Figure 10, as described in section II-E. Given an exosystem class  $\mathcal{W}_d$  we denote by  $\mathcal{C}$  a class of control systems for which such a network is defined. Since the network parameters  $P \wedge C \wedge W$  (together with the inputs) determine the dynamical evolution of the plant-controller-exosystem network, control design can be thought of in terms of shaping the network dynamics in a desired way by appropriate choice of controller  $C \in \mathcal{C}$ . Note that this framework is general enough to allow us to consider choices for the controller that are quantum, or classical, or a mixture of the two (cf. [17]).




Fig. 10. The plant-controller-exosystem network  $P \wedge C \wedge W$ .

It is worth remarking that the distinction between plant and controller is not always clear-cut. Indeed, the plant may need to be engineered in an appropriate way to facilitate control. For example, one may desire certain field couplings or direct interaction Hamiltonians to be physically available—this clearly relates to the design of the plant. This issue, of course, is not unknown in classical control engineering, and is evident in the examples below. Also, if one is interested in the expected behavior of the network for a range of variables  $X$ , then it may be appropriate to work directly with the network generator  $\mathcal{G}_{P \wedge C \wedge W}(X)$ , and use the form of this generator to determine the controller  $C$ , given the objectives. This approach is roughly dual to a method based on master equations already in use, see, e.g. [30].

We specify the control objectives by encoding them in a non-negative observable  $V_d \in \mathcal{A}_P \otimes \mathcal{A}_C$  (the parameters of the controllers  $C \in \mathcal{C}$  are assumed to belong to  $\mathcal{A}_C$ ), a supply rate  $r_d(W)$ , and a class of exosystems  $\mathcal{W}_d$  for

which a network  $(P \wedge C) \wedge W$  is well defined. One then seeks to find, if possible, a controller  $C \in \mathcal{C}$  such that

$$\mathcal{G}_{P \wedge C \wedge W}(V_d) - r_d(W) \leq 0 \quad (81)$$

for all exosystem parameters  $W \in \mathcal{W}_d$ . In other words, one seeks a controller for which the closed loop system is dissipative with storage function  $V_d$ , supply rate  $r_d(W)$ , and exosystem class  $\mathcal{W}_d$ . The exosystems are included to facilitate robust control system design for situations where uncertainty and disturbances are important. The observable  $V_d$  is something which on average should be small (such as regulation errors), or tend to zero as time evolves. The supply rate may also contain such “small” quantities, as well as terms from the exosystems. The supply rate need not be the natural supply rate for the network—the inequality in the dissipation inequality can be exploited to permit other choices.

### B. Controller Synthesis

We shall now describe how standard problems of stabilization, regulation, and robust control fall within the scope of the controller synthesis framework formulated in the previous subsection. We begin with a general synthesis problem that abstracts stabilization and regulation, since they are closely related. These problems correspond to a choice  $V_d$  of a non-negative observable whose expected value we wish to go to zero as time approaches infinity. For definiteness, we choose  $r_d(W) = -cV_d$ , where  $c > 0$  is a suitable real number, and  $\mathcal{W}_d = \{(-, -, 0)\}$ , which consists only of the trivial exosystem, so that  $(P \wedge C) \wedge W = (P \wedge C) \boxplus (-, -, 0) = P \wedge C$ .

*Theorem 4.1:* (Stabilization/regulation) If there exists a controller  $C \in \mathcal{C}$  and non-negative observable  $V_d \in \mathcal{A}_P \otimes \mathcal{A}_c$  such that the plant-controller network  $P \wedge C$  satisfies

$$\mathcal{G}_{P \wedge C}(V_d) + cV_d \leq 0 \quad (82)$$

for some real  $c > 0$ , then  $\langle V_d(t) \rangle \rightarrow 0$  as  $t \rightarrow \infty$  exponentially for any plant-controller state.

This theorem follows from the stability results give in subsection III-B.

Our next result is a general theorem concerning nonlinear quantum  $H^\infty$  robust control, which generalizes the linear quantum results given in [17], [19]. We use an exosystem class  $\mathcal{W}_d = \{W : W = (I, w, 0) : w \text{ commutes with } \mathcal{A}_P\}$  to describe the “disturbance” inputs. The next theorem is a consequence of a slight extension of the Bounded Real Lemma (Theorem 3.7) applied to the plant-controller network  $P \wedge C$ .

*Theorem 4.2:* ( $H^\infty$  control) If there exists a controller  $C \in \mathcal{C}$  and a non-negative observable  $V_d \in \mathcal{A}_P \otimes \mathcal{A}_c$  such that the plant-controller network  $P \wedge C$  satisfies

$$g^2 - Z^\dagger Z \geq 0 \quad (83)$$

and

$$\mathcal{G}_{(P \wedge C) \wedge W}(V_d) - g^2 w^\dagger w + (N + Zw)^\dagger (N + Zw) - \lambda \leq 0 \quad (84)$$

for some real  $g > 0$ ,  $\lambda \geq 0$ , and all exosystem parameters  $W \in \mathcal{W}_d$ , then the plant-controller network  $P \wedge C$  has gain  $g$ .

### C. Design Examples

In this section we provide some simple examples to illustrate several issues concerning feedback control design of quantum systems. The examples (Examples 4.3, 4.4) employ the series architecture shown in Figure 11.




Fig. 11. The plant-controller network  $P \triangleleft C$  for Examples 4.3, 4.4.

Our first design example is a regulation problem analogous to the classical problem of designing a controller to maintain a given value of capacitor charge in a RC circuit, [27].

*Example 4.3: (Regulation)* Consider an optical cavity  $P = (1, a, 0)$  (a damped open harmonic oscillator, Example 3.10). If the input field is a vacuum, photons initially in the cavity will eventually leak out. Suppose our control objective is to maintain a given non-zero value for the steady state expected photon number. Let's choose a value  $\alpha$  for the desired steady-state value of  $a$ , which corresponds to a number  $\alpha^* \alpha$  of photons (i.e., we want the cavity to be in a coherent state  $|\alpha\rangle$  in the steady-state, Appendix B).

Perhaps the simplest thing to do is to provide a source of fresh photons that can be supplied to the cavity to replace those that are lost. This might be achieved using a laser source or modulator  $C = (1, \nu, 0)$  connected in series, as in Figure 11. Here,  $\nu$  is a complex number describing the strength of the source, and is to be determined, if possible.

We set

$$V_d = (a - \alpha)^*(a - \alpha) = a^*a - \alpha^*a - a^*\alpha + \alpha^*\alpha,$$

and for a positive real number  $c$ ,

$$r_d(W) = -cV_d,$$

with  $\mathcal{W}_d = \{(-, -, 0)\}$ , which consists only of the trivial exosystem, as in Theorem 4.1. Note that the expected value of  $V_d$  in the state  $\alpha$  is zero:  $\langle \alpha | V_d | \alpha \rangle = 0$ .

The design problem is to select  $\nu$ , a complex number, such that

$$\mathcal{G}_{P \triangleleft C}(V_d) + cV_d \leq 0$$

for suitable  $c > 0$ . Then from (26) the LHS of this expression is

$$-a^*a(1 - c) + a\left(\frac{\alpha^*}{2} - \nu^* - c\alpha^*\right) + a^*\left(\frac{\alpha}{2} - \nu - c\alpha\right) + \alpha^*\nu + \alpha\nu^* + c\alpha^*\alpha.$$

If we set  $c = 1/2$ ,  $\nu = -\alpha/2$ , then this expression equals  $-V_d/2$ . Therefore

$$\mathcal{G}_{P \triangleleft C}(V_d) \leq -V_d/2$$

which implies that the expected value of  $V_d(t)$  tends to zero as  $t \rightarrow \infty$  (by Theorem 3.5), and the control objective is achieved (notes also that the expected value of  $P \triangleleft C$  in the cavity coherent state  $|\alpha\rangle$  is zero:  $\langle \alpha | \mathcal{G}_{P \triangleleft C}(V_d) | \alpha \rangle = 0$ ).

The effect of the controller is to place the cavity input field in a coherent state  $|\nu\rangle$ . It is well known (e.g. [10]) that this is equivalent to adding a Hamiltonian term to the cavity model and setting the input to vacuum. In the notation of this paper, this follows from (25) and (26):  $\mathcal{G}_{P \triangleleft C}(X) = \mathcal{G}_{P \boxplus \tilde{C}}(X)$ , where  $\tilde{C} = (-, -, -i(\nu a^* - \nu^* a))$ . This is illustrated in Figure 12.  $\square$




Fig. 12. Alternate representation of the plant-controller network  $P \triangleleft C$  in the form  $P \boxplus \tilde{C}$  for Example 4.3.

The next example shows that care must be exercised when attempting to use classical control design methods. Furthermore, one must take account of quantum noise and the fact that physical quantities do not in general commute.

*Example 4.4:* (Stabilization) Suppose we wish to stabilize the marginally stable system  $P = (1, a + a^*, 0)$ , a special case of the open oscillators of Example 3.10, using an approach analogous to a standard method from classical control theory for stabilizing Hamiltonian systems, [32, sec. 4.1].

Consider the series plant-controller network of Figure 11. From Example 3.10, we know that this system is passive; if  $C = (1, u, 0)$  then

$$\mathcal{G}_{P \triangleleft C}(V_0) = \mathcal{L}_u(V_0) + u^* Z + Z^* u + 1, \quad (85)$$

where  $Z = a^* - a$  and  $V_0 = a^* a$  (recall (38), (64) with  $W = C$ ). The classical Hamiltonian stabilization procedure suggests that we set

$$u = -kZ \quad (86)$$

for some non-negative gain  $k$ . In order to implement this feedback, the controller  $C$  needs to have access to the variable  $Z$ . However,  $Z$  is not available in the output signal  $\tilde{B}$ , since by the output relation (21)  $d\tilde{B} = Ldt + dB$ , where  $L = a + a^*$ .

We suppose that the plant can be re-engineered to have a second field channel which contains  $Z$ . Specifically, we consider the augmented system  $P \boxplus C$ , where  $C = (1, -kZ, 0)$ . The desired variable is now available in the second output of the augmented system, and so we can form the series connection  $P \triangleleft C = (1, (1+k)a + (1-k)a^*, -ik(a^2 - (a^*)^2))$ , Figure 13. However, an examination of the dynamics of the quadratures  $q = a + a^*$  and

$p = -i(a - a^*)$  shows that the feedback system  $P \triangleleft C$  is marginally stable and not asymptotically stable for all  $k \geq 0$  (the feedback system has poles at 0 and  $-4k$ ). Physically, neither of the field couplings  $L = a + a^* = q$  and  $-kZ = k(a - a^*) = ikp$  are sufficient for strict passivity and hence asymptotic stability.

A preferable stabilization scheme would be to replace  $C$  by  $\tilde{C} = (1, ka, 0)$ . Then the re-engineered systems  $P \boxplus \tilde{C}$  and  $P \triangleleft \tilde{C}$  are both strictly passive and asymptotically stable.

Note that the ability to engineer field couplings is of fundamental importance here (see [23] for general results concerning physical realization in the context of linear quantum systems).




Fig. 13. Alternative representation of the plant-controller network  $P \triangleleft C$  for Example 4.4.

□

## V. CONCLUSIONS

In this paper we have extended J.C. Willems' theory of dissipative systems to the quantum domain. The quantum systems we considered are open quantum models, and with the aid of recently developed methods for describing quantum feedback networks, we have shown how to describe external influences as arising from interactions with exosystems. The fundamental dissipation property was expressed in these terms. We presented an infinitesimal characterization of the dissipation property, which generalizes the well-known Positive Real and Bounded Real Lemmas. We also showed how to implement Willems' "control by interconnection" for open quantum systems using quantum network representations.

We believe that the results in this paper provide useful methods for the analysis and design of quantum dissipative systems, and indeed networks of such systems. The quantum network based results we have presented are quite general and powerful, and merit further development. The network paradigm is particularly important if quantum technology is to move from the device and small system level to a more complex system level such as is being contemplated, for example, in the quantum computing community.

## APPENDIX

### A. Two Level Atom (Qubit)

The simplest quantum system has two energy levels and is often used to model ground and excited states of atoms. Since the advent of quantum computing, this system is also known as the qubit, the unit of quantum information.

The two level atom is illustrated in Figure 14 (a), showing the action of the raising  $\sigma_+$  and lowering  $\sigma_-$  operators. The Hilbert space for this system is  $H = \mathbf{C}^2$ , the two-dimensional complex vector space. The physical variable space  $\mathcal{A}$  for this system is spanned by the Pauli matrices [22, sec. 2.1.3], [10, sec. 9.1.1]:

$$\sigma_0 = I = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix}, \quad \sigma_x = I = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}, \quad \sigma_y = I = \begin{pmatrix} 0 & -i \\ i & 0 \end{pmatrix}, \quad \sigma_z = I = \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}.$$

The raising and lowering operators are defined by  $\sigma_{\pm} = \frac{1}{2}(\sigma_x \pm i\sigma_y)$ . The basic commutation relations are  $[\sigma_x, \sigma_y] = 2i\sigma_z$ ,  $[\sigma_y, \sigma_z] = 2i\sigma_x$ , and  $[\sigma_z, \sigma_x] = 2i\sigma_y$ . The energy levels correspond to the eigenvalues of  $\sigma_z$ .




Fig. 14. Energy level diagrams. (a) Two-level atom (qbit). (b) Harmonic oscillator.

### B. Quantum Harmonic Oscillator

The quantum harmonic oscillator is one of the most important examples because of its tractability and application to modeling, [22, Box 7.2], [20, sec. 10.6], [10, sec. 4.1]. Models for the optical cavity and boson fields are based on the quantum harmonic oscillator. The quantum harmonic oscillator is illustrated in Figure 14 (b), which shows infinite ladder of energy levels and the action of the creation  $a^*$  and annihilation  $a$  operators. The Hilbert space for the quantum harmonic oscillator is  $H = L^2(\mathbf{R}, \mathbf{C})$ , the vector space of square integrable functions defined on the real line. The physical variable space  $\mathcal{A}$  for this system is defined in terms of the annihilation operator  $a$ , with  $a^*$  the adjoint of  $a$ , and the *canonical commutation relations*  $[a, a^*] = 1$ . The action of the annihilation operator may be expressed as

$$(a\psi)(x) = x\psi(x) - i\frac{d\psi}{dx}(x)$$

on a domain of functions (vectors)  $\psi$  in  $H$ . The eigenvalues of  $a^*a$  are the numbers  $0, 1, 2, \dots$  (number of quanta), with corresponding eigenvectors denoted  $\psi_n$  ( $n = 0, 1, 2, \dots$ ) called *number states*. We have  $a\psi_n = \sqrt{n}\psi_{n-1}$  and  $a^*\psi_n = \sqrt{n+1}\psi_{n+1}$ . For a complex number  $\alpha$ , a *coherent state* is defined by

$$|\alpha\rangle = \exp\left(-\frac{1}{2}|\alpha|^2\right) \sum_{n=0}^{\infty} \frac{\alpha^n}{\sqrt{n!}} \psi_n$$

(Dirac notation), and satisfies the eigenvalue relation  $a|\alpha\rangle = \alpha|\alpha\rangle$ .

### C. Operator Orderings

In this appendix we review some definitions and results concerning operator ordering.

Let  $A$  and  $B$  be self-adjoint operators on a Hilbert space  $H$ . Then by definition  $A \geq 0$  means  $\langle \psi, A\psi \rangle \geq 0$  for all vectors  $\psi \in H$ . Using this, we say  $A \geq B$  to mean  $A - B \geq 0$ .

Now fix  $A$  and  $B$  self-adjoint, and  $C$  is arbitrary. Assume

$$w^*Aw \leq B + w^*C + C^*w \quad (87)$$

for all operators  $w$  acting on  $H$ . Then we claim that  $A \leq 0$ .

To verify this claim, suppose by contradiction there exists  $\psi_0 \in H$  such that

$$\langle \psi_0, A\psi_0 \rangle > 0. \quad (88)$$

Now set  $w = \alpha I$ , where  $\alpha$  is an arbitrary real number. Then (87) implies

$$\alpha^2 \langle \psi_0, A\psi_0 \rangle \leq \langle \psi_0, B\psi_0 \rangle + \alpha \langle \psi_0, (C + C^*)\psi_0 \rangle. \quad (89)$$

Since  $\alpha$  is arbitrary, this contradicts (88), establishing the claim.

Now fix arbitrary operators  $C$  and  $D$ . We can use a similar argument to show that if

$$w^*C + C^*w \leq D \quad (90)$$

for all operators  $w$  acting on  $H$ , then  $C = 0$ .

**Acknowledgement.** The authors wish to thank Guofeng Zhang for his helpful comments.

### REFERENCES

- [1] L. Bouten, R. Van Handel, and M.R. James. An introduction to quantum filtering. *SIAM J. Control and Optimization*, 46(6):2199–2241, 2007.
- [2] H. Carmichael. *An Open Systems Approach to Quantum Optics*. Springer, Berlin, 1993.
- [3] H.J. Carmichael. Quantum trajectory theory for cascaded open systems. *Phys. Rev. Lett.*, 70(15):2273–2276, 1993.
- [4] C. D’Helon and M.R. James. Stability, gain, and robustness in quantum feedback networks. *Phys. Rev. A*, 73:053803, 2006.
- [5] A.C. Doherty and K. Jacobs. Feedback-control of quantum systems using continuous state-estimation. *Phys. Rev. A*, 60:2700, 1999.
- [6] P. Dupuis, M.R. James, and I.R. Petersen. Robust properties of risk-sensitive control. *Math. Control, Systems and Signals*, 13:318–332, 2000.
- [7] W.H. Fleming and M.R. James. The risk-sensitive index and the  $H_2$  and  $H_\infty$  norms for nonlinear systems. *J. Mathematics of Control, Signals, and Systems*, 8:199–221, 1996.
- [8] C.W. Gardiner. Driving a quantum system with the output field from another driven quantum system. *Phys. Rev. Lett.*, 70(15):2269–2272, 1993.
- [9] C.W. Gardiner and M.J. Collett. Input and output in damped quantum systems: Quantum stochastic differential equations and the master equation. *Phys. Rev. A*, 31(6):3761–3774, 1985.
- [10] C.W. Gardiner and P. Zoller. *Quantum Noise*. Springer, Berlin, 2000.
- [11] J. Gough and M.R. James. Quantum feedback networks: Hamiltonian formulation. *to appear, Commun. Math. Phys.*, 2008. quant-ph/0804.3442.
- [12] J. Gough and M.R. James. The series product and its application to quantum feedforward and feedback networks. *to appear, IEEE Trans. Automatic Control*, arxiv.org/quant-ph/0707.0048 2008.

- [13] M. Green and D.J.N. Limebeer. *Linear Robust Control*. Prentice-Hall, Englewood Cliffs, NJ, 1995.
- [14] D. Hill and P. Moylan. The stability of nonlinear dissipative systems. *IEEE Transactions on Automatic Control*, AC-21:708–711, 1976.
- [15] D. Hill and P. Moylan. Dissipative dynamical systems: Basic input-output and state properties. *Journal of the Franklin Institute*, 309:327–357, 1980.
- [16] R.L. Hudson and K.R. Parthasarathy. Quantum Ito’s formula and stochastic evolutions. *Commun. Math. Phys.*, 93:301–323, 1984.
- [17] M.R. James, H. Nurdin, and I.R. Petersen.  $H^\infty$  control of linear quantum systems. *IEEE Trans. Automatic Control*, 53(8):1787–1803, 2008.
- [18] S. Lloyd. Coherent quantum feedback. *Phys. Rev. A*, 62:022108, 2000.
- [19] H. Mabuchi. Coherent-feedback quantum control with a dynamic compensator. arXiv:0803.2007 2008.
- [20] E. Merzbacher. *Quantum Mechanics*. Wiley, New York, third edition, 1998.
- [21] P.J. Moylan. Implications of passivity in a class of nonlinear systems. *IEEE Trans. Automatic Control*, 19(4):373–381, 1974.
- [22] M.A. Nielsen and I.L. Chuang. *Quantum Computation and Quantum Information*. Cambridge University Press, Cambridge, 2000.
- [23] H. Nurdin, M.R. James, and A.C. Doherty. Network synthesis of linear dynamical quantum stochastic systems. *SIAM J. Control and Optimization*, to appear, arXiv:0806.4448v1 2009.
- [24] H. Nurdin, M.R. James, and I.R. Petersen. Coherent quantum LQG control. *Automatica*, to appear, arXiv:0711.2551 2009.
- [25] H. Nyquist. Thermal agitation of electric charge in conductors. *Phys. Rev.*, 32:110–113, 1928.
- [26] R. Ortega and M.W. Spong. Adaptive motion control of rigid robots: A tutorial. *Automatica*, 25(6):877–888, 1989.
- [27] R. Ortega, A. J. van der Schaft, I. Mareels, and B. Maschke. Putting energy back in control. *IEEE Control Systems Magazine*, 21:18–32, April 2001.
- [28] R. Ortega, A. J. van der Schaft, B. Maschke, and G. Escobar. Interconnection and damping assignment passivity-based control of port-controlled Hamiltonian systems. *Automatica*, 38:585–596, 2002.
- [29] K.R. Parthasarathy. *An Introduction to Quantum Stochastic Calculus*. Birkhauser, Berlin, 1992.
- [30] L.K. Thomsen and H.M. Wiseman. Atom-laser coherence and its control via feedback. *Phys. Rev. A*, 65:063607, 2002.
- [31] H.L. Trentelman and J.C. Willems.  $H_\infty$  control in a behavioral context: The full information case. *IEEE Trans. Automatic Control*, 44(3):521–536, 1999.
- [32] A.J. van der Schaft.  *$L_2$ -Gain and Passivity Techniques in Nonlinear Control*. Springer Verlag, New York, 1996.
- [33] R. van Handel, J. Stockton, and H. Mabuchi. Feedback control of quantum state reduction. *IEEE Trans. Automatic Control*, 50:768–780, 2005.
- [34] J.C. Willems. Dissipative dynamical systems - Part I: General theory. *Archive of Rational Mechanics and Analysis*, 45:321–351, 1972.
- [35] J.C. Willems. On interconnections, control, and feedback. *IEEE Trans. Automatic Control*, 42(3):326–339, March 1997.
- [36] J.C. Willems. Open dynamical systems and their control. *Documenta Mathematica*, Extra Vol. ICM(III):697–706, 1998.
- [37] J.C. Willems. Control as interconnection. In *Feedback Control, Nonlinear Systems and Complexity*, Lecture Notes in Control and Information Science. Springer, 2003.
- [38] J.C. Willems and H.L. Trentelman. Synthesis of dissipative systems using quadratic differential forms: Part I. *IEEE Trans. Automatic Control*, 47(1):53–69, 2002.
- [39] H. M. Wiseman and G. J. Milburn. All-optical versus electro-optical quantum-limited feedback. *Phys. Rev. A*, 49(5):4110–4125, 1994.
- [40] M. Yanagisawa and H. Kimura. Transfer function approach to quantum control-part I: Dynamics of quantum feedback systems. *IEEE Trans. Automatic Control*, (48):2107–2120, 2003.
- [41] M. Yanagisawa and H. Kimura. Transfer function approach to quantum control-part II: Control concepts and applications. *IEEE Trans. Automatic Control*, (48):2121–2132, 2003.
- [42] B. Yurke and J.S. Denker. Quantum network theory. *Phys. Rev. A*, 29(3):1419–1437, 1984.
- [43] G. Zames. On the input-output stability of time-varying nonlinear feedback systems Part I: Conditions derived using concepts of loop gain, conicity, and positivity. *IEEE Trans. Automat. Control*, 11(2):228–238, 1966.
- [44] K. Zhou, J. Doyle, and K. Glover. *Robust and Optimal Control*. Prentice Hall, NJ, 1996.